

Example Prerequisites

This section walks through configuring Microsoft Word 2016 to work with the Conversion Server. Before proceeding, take the time to review these requirements.

Aras Innovator Conversion Server

Before proceeding, you need to install the Conversion Server.

To install the conversion server, refer to the *Aras Innovator 40 - Conversion Server Setup Guide*.

Microsoft Visual C++ Redistributable Package

You must install The Microsoft Visual C++ 2015, 2017, 2019, and 2022 Redistributable Packages on the Conversion Server. The links to these downloads can be found at Microsoft's latest supported Visual C++:

Microsoft Visual C++ 2015, 2017, 2019, and 2022 Redistributable Packages (x64):

<https://support.microsoft.com/en-us/help/2977003/the-latest-supported-visual-c-downloads>

Microsoft Word 2016

For this example to work, Microsoft Word 2016 must be configured to launch using the interactive user and must have the correct permissions. This is configured in the DCOM Config under Component Services:

1. Select **Start -->Run**.
2. Type `dcomcnfg` and click **OK**.
3. Expand **Component Services -->Computers -->My Computer -->DCOM Config**.
4. Right click on the Microsoft Word 97 – 2003 Document and select **Properties**.
5. Click the **Security** tab.
6. Select **Customize** under **Launch and Activation Permissions** and click **Edit**.
 1. Add "IIS_IUSRS" and set **Allow** for **Local Launch** and 'Local Activation.'
 2. Click **OK**.
7. Select **Customize** under **Access Permissions** and click **Edit**.
 1. Add "IIS_IUSRS" and set **Allow** for **Local Access**.



2. Click **OK**.
8. Select the **Identity** tab and select the **Theinteractive user** option.
9. Click **Apply** and then **OK**.
10. Close the Component Services window.

