

Installing Aras Innovator

The first step in installing Aras Workspace Productivity Connector 33 is to set up the Aras Innovator instance. This section describes the three major steps for setting up your Aras Innovator instance with Aras Workspace Productivity Connector 33.

Aras Innovator

Important

Subscribers can download the Aras Innovator CD image from the [Aras MFT](#) site located in the **Innovator Latest Release** folder.

You can find the Aras Innovator installation guide in the **Documentation** folder of the CD image.

At release, Aras Workspace Productivity Connector 33 supports **Aras Innovator 33**. (If you're using an earlier version, please upgrade before installing the connector.)

- The Workspace Productivity Connector requires HTTPS, so your Aras Innovator instance must be configured to use HTTPS.
- If you need help upgrading, contact Aras Support at the [Aras Subscriber Portal](#) before installing the connector.

Confirming the Aras Innovator Installation

Follow this procedure to check if the Aras Innovator Code Tree and database meet the minimum requirements to apply the Aras Workspace Productivity Connector Solution AML:

1. Log into Aras Innovator as an administrator.
2. Click the **User** icon in the top-right corner and select **About**.
3. Confirm that the dialog shows **Release33**.
4. Close the dialog.
5. From the **TOC**, expand **Administration** and select **Variables**.
6. Confirm that the following variables are listed:



Version Major	Version Minor	VersionServiceUpdate	VersionLabel
14	0	30	Release 33

Feature License Key

Aras Workspace Productivity Connector 33 requires a valid Feature License to run. To check if one is installed:

1. Log into Aras Innovator as an administrator.
2. In the TOC, expand **Administration** and select **Feature Licenses**.
3. Look for the **Aras.WorkspaceProductivityConnector** license. If it's listed, check the expiration date to ensure it's still active.

Requesting a Feature License

To request a Feature License activation key, customers with an active Aras subscription can **send an email to licenses@aras.com** or **contact their account representative** using the subject and body:

Subject Aras Workspace Productivity Connector Activation Key Required

Body *Version of Aras Innovator*

You'll receive a reply with the activation key.

Installing the License

Once you have the activation key, you can install the feature license:

- Log into Aras Innovator as an administrator.
- Click the **User** icon in the top-right corner and click **Activate Feature**.
- Paste the acquired activation key and click **Activate**. You will see a success message.

