



# Change Banner

The following steps outline the process of updating the banner logo:


1. Navigate to the existing image.
2. Login into the Aras Innovator instance.
3. From the **Table of Contents**, expand **Administration** and **Configuration**, then select **Client Presentation**.



4. From **Client Presentation** Table of Contents, click **Search Client Presentation**.



5. On **Client Presentation** Form, click the **Search** button then click the **Global** link.



6. In **Command Bar Section** Tab, select the row with the **Main Window Header** label.

Global ☆ □

Command Bar Section cui\_PresentConfigWinSection Presentation Command

CommandBarSection ☆

#	Classification	Name	Builder Meth...	Label	Description	Additional De...	Location [...]	sort_Lander	For Identity [...]	For Classifa...
	Data Model	com.aras.inno...	extendedManipViewerToolBar			{'buttonstyle'...	extendedMdr...	5376	World	
	Method	com.aras.inno...	CuiMdrView...				PopUpMenu1...	5760	World	
	Method	com.aras.inno...	CuiMdrView...				PopUpMenu1...	6144	World	
	Method	com.aras.inno...	CuiMdrView...				PopUpMenu1...	6028	World	
	Data Model	com.aras.inno...	Default TOV Toolbar				TOV_Toolbar	6656	World	
	Data Model	com.aras.inno...	TOV Context Menu Default				TOV_Context...	6764	World	
	Data Model	com.aras.inno...	Main Window Header				MainWindow...	6912	World	
	Data Model	com.aras.inno...	Effectivity Expression Item Grid T...				eff_Leaves...	6912	World	
	Data Model	com.aras.inno...					MainWindow...	7040	World	
	Method	com.aras.inno...	cui_default...				TOV	7168	World	
	Data Model	itemview/ite...	Item View Default Command Bar				CommandBar...	7296	World	

7. Select `com.aras.innovator.cui_default.mwh_header_logo`.

Client Presenta... X Global X com.aras.innov... X com.aras.innov... X Client Presenta... X

com.aras.innovator.cui\_default.mwh\_header ☆ □

Location: MainWindowHeader

Classification: Data Model

Label: Main Window Header

Description:

Command Bar Item Command Bar Section Dependency


CommandBarItem ☆

#	ItemType	Name	Additional ...	Init Method [...]	Sort Order	Action	Alternate [...]	For Identity [...]	For Classifa...
	Button	com.aras.innovator.cui_default.mwh_header_navip...	{'clickEventT...		18	Add		World	
	Button	com.aras.innovator.cui_default.mwh_header_logo	{'type': 'img...		32	Add		World	
	Button	com.aras.innovator.cui_default.mwh_header_copost...	{'right': true, '...	cui_default...	64	Add		World	
	Button	com.aras.innovator.cui_default.mwh_header_splitacc...	{'right': true}	cui_default...	86	Add		World	
	Button	com.aras.innovator.cui_default.mwh_header_notificat...	{'right': true, '...	cui_default...	128	Add		World	

< Prev Next > Page: 1 of 1 | 5 Results

8. Notice the existing image. The height is significant for adjusting the customer's logo to fit while maintaining conformity with the customer's branding guidelines.





9. On the local machine, add the required Customer Logo in the following directory:  
 C:\{working directory}\Instances\dev\OAuthServer\wwwroot\images  
 The image should be in SVG format.
10. Navigate to the following folder: C:\{Working Directory}\AML-  
 packages\com\aras\innovator\cui\_default\CommandBarButton
11. Open the com.aras.innovator.cui\_default.mwh\_header\_logo file.
12. In the com.aras.innovator.cui\_default.mwh\_header\_logo file, do the following:
  - o Change the action attribute from add to edit.
  - o Add the CustomerLogo.svg in the image **Tag**. Ensure that the path is correct.

```
<XML>
<Item type="CommandBarButton" id="83E579F86F0848508927F070D099091E" action="add">
  <additional_data type="image", cssClass="aras-header_logo", attributes: { "aria-hidden": true } ></additional_data>
  <image ../images/CustomerLogo.svg /image>
  <name>com.aras.innovator.cui_default.mwh_header_logo</name>
</Item>
</XML>
```

13. Run the **./BuildAndDeploy.ps1** script to rebuild the Aras Innovator instance. The Banner will now be the new image.

